

**STEVIA IN SEEDBEDS**

<b>STAGE</b>	<b>PRODUCT</b>	<b>Application Rate</b>
Fumigation	Basamid GR or	Apply 60g/m <sup>2</sup> . Mix to 200mm deep & irrigated to 60% capacity and cover with tent for 7 days
Fumigation	Metham Sodium	Drench 100mls in 4lts water/m <sup>2</sup> . Seal with tent for 7 days
Beds Making	Single Super Phosphate	12g/m <sup>2</sup>
Beds Making	Kynobor	5g per 36m <sup>2</sup> bed
Before Sticking	Copper Oxychloride	Apply 150g/36m <sup>2</sup> with 40lts water
At Sticking	Seradix B No 1	Dip cuttings into Seradix
After Sticking	Kynopop	Apply 250g/36m <sup>2</sup> in 40lts water
1 Week After Sticking	Copper Oxychloride	Apply 150g/36m <sup>2</sup> with 40lts water
1 Week After Sticking	Sporekill	Apply with Knapsack (50mls Sporekill per knapsack)
2 Weeks After Sticking	Veggie Oemff Starter	Apply 8g/36m <sup>2</sup> with 40lts water
2 Weeks After Sticking	Copper Oxychloride	Apply 150g/36m <sup>2</sup> with 40lts water
2 Weeks After Sticking	Sporekill	Apply with Knapsack (50mls Sporekill per knapsack)
3 Weeks After Sticking	Veggie Oemff Starter	Apply 8g/36m <sup>2</sup> with 40lts water
3 Weeks After Sticking	Potassium Nitrate Greenhouse	Apply 1g/m <sup>2</sup>
3 Weeks After Sticking	Copper Oxychloride	Apply 150g/36m <sup>2</sup> with 40lts water
3 Weeks After Sticking	Sporekill	Apply with Knapsack (50mls Sporekill per knapsack)
4 Weeks After Sticking	Calsap	Add 12mls per knapsack. 1 knapsack to 4 beds
4 Weeks After Sticking	Copper Oxychloride	Apply 150g/36m <sup>2</sup> with 40lts water
4 Weeks After Sticking	Sporekill	Apply with Knapsack (50mls Sporekill per knapsack)
Before Planting	Kynopop	Apply 250g/36m <sup>2</sup> in 40lts water
Before Planting	Potassium Nitrate Greenhouse	Apply 1g/m <sup>2</sup>